



JÄRBO

92629



Tjárn - child's cap

This cap is knitted in the round from the bottom up. If you like, you can add earflaps and a pompom to the cap.

LEVEL OF DIFFICULTY **

SIZES 6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

FINISHED MEASUREMENTS

Circumference approx. 15 (17, 17, 19, 19) in / 38 (43, 43, 48, 48) cm

Length: approx. 7 (8, 8¼, 9, 9) in / 19 (20, 21, 23, 23) cm

YARN CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Mellanraggi (75% wool, 25% polyamide, 284 yd/260 m / 100g)

CYCA #3 (DK, light worsted), Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Lady (100% acrylic, 138 yd/126 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Svensk Ull (100% Swedish wool, 197 yd/180 m / 100 g)

YARN COLORS AND AMOUNTS

Color A: Natural White 18402: approx. 15 (15, 15, 15) g

Color B: Dark Teal 18417 or Spicy Curry 18424: approx. 20 (25, 25, 30, 30) g + approx. 10 (15, 15, 15, 15) g extra for earflaps

Color C: Tobacco Brown 18404: approx. 15 (15, 15, 15) g

Optional: approx. 20 g for pompom in desired color

NEEDLES U. S. sizes 4 and 6 / 3.5 and 4 mm: 16 in / 40 cm circulars; sets of 5 dpn

GAUGE

Approx. 21 sts x 27 rnds on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

Decrease 1 to left (ssk): (Sl 1 knitwise) 2 times, place sts back on left needle and k2tog through back loops.

BEGIN with RIBBED BRIM

With color B and smaller size circular, CO 80 (90, 90, 100, 100) sts. Join, being careful not to twist cast-on row; pm for beginning of rnd.

Work around in k1, p1 ribbing for approx. 1¼ (1¼, 1½, 1½, 2) in / 3 (3, 4, 4, 5) cm or desired length.

Change to larger size circular and knit 1 rnd.

Work around in pattern following chart, working 1 rep in length.

Continue with color A only until piece measures 5 (5¼, 5½, 5¾, 6) in / 12.5 (13, 14, 14.5, 15) cm.

CROWN SHAPING

Change to dpn when sts no longer fit around circular.

Decrease Rnd 1: *K6 (7, 7, 8, 8), k2tog*; rep * to * around = 70 (80, 80, 90, 90) sts rem.

Knit 2 rnds.

Decrease Rnd 2: *K5 (6, 6, 7, 7), k2tog*; rep * to * around.

Knit 2 rnds.

Continue as est, with 1 less st between decreases on every 3rd rnd another 3 (4, 4, 5, 5) times until 10 sts rem.

Cut yarn and draw end through rem sts; tighten. If desired, make a pompom and sew it securely to top of cap.

EARFLAPS

With color B and smaller size circular, starting at beginning of rnd, pick up and knit 23 (25, 27, 29, 31) sts along inside of cap, on the 1st rnd after the ribbing.

RS: K2, *k1, p1*; rep * to * around, ending with k1.

WS: Turn and sl 2 sts wyb; also slip last 2 sts of row wyb. The slipped sts form a thin I-cord edge for flaps. For rest of sts on the row, work knit over knit and purl over purl.

Continue working back and forth as est until flap is same length as ribbing.

Next RS Row: K2, ssk, work in ribbing until 4 sts rem, k2tog, k2.

WS: Work as for previous WS rows.

Rep these 2 rows until 7 sts rem.

K2, sl 1, k2tog, pssso, k2 = 5 sts rem.

Work rem 5 sts as I-cord: Work with RS facing throughout.

Slide sts to end of dpn. Pull yarn behind sts and k5. Rep * to * until cord is about 6-8 in / 15-20 cm long. Cut yarn and fasten off.

Second earflap: Measure so there is about 2¼ (2 3/8, 2½, 2¾, 3) in / 5.5 (6, 6.5, 7, 7.5) cm between the earflaps at center back of cap. Make sure that the centering will be at rnd changes on back of cap.

With color B and smaller size circular, pick up and knit 23 (25, 27, 29, 31) sts along inside of cap, on the 1st rnd after ribbing. Work flap as for first one.



FINISHING

Weave in all ends neatly on WS.

SCHEMATICS

A 15 (17, 17, 19, 19) in / 38 (43, 43, 48, 48) cm

B 7 (8, 8¼, 9, 9) in / 19 (20, 21, 23, 23) cm



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92628



Tjörn - child's tunic

This tunic is knitted from the top down with raglan shaping for the yoke. The neckband is held in with a crocheted tie.

LEVEL OF DIFFICULTY **

SIZES

6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

European sizes 74-80 (86-92, 98-104, 110-116, 122-128) CL

FINISHED MEASUREMENTS

Chest: approx. 19 (22½, 24½, 26½) in / 48 (52, 57, 62, 67) cm

Total Length: approx. 14¼ (16¼, 18¼, 20½, 22½) in / 36 (41, 46, 52, 57) cm

Sleeve length: approx. 8¼ (9½, 10¾, 11¾, 13) in / 21 (24, 27, 30, 33) cm

YARN CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Mellanraggi (75% wool, 25% polyamide, 284 yd/260 m / 100g)

CYCA #3 (DK, light worsted), Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Lady (100% acrylic, 138 yd/126 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Svensk Ull (100% Swedish wool, 197 yd/180 m / 100 g)

YARN COLORS AND AMOUNTS

Color A: Heather Beige 18405: approx. 110 (130, 160, 180, 200) g

Color B: Natural White 18402: approx. 15 (15, 20, 20, 20) g

Color C: Tobacco Brown 18404: approx. 10 (10, 10, 10, 10) g

Color D: Dark Teal 18417: approx. 15 (15, 20, 20, 25) g

NEEDLES U. S. sizes 4 and 6 / 3.5 and 4: 24/32 in / 60/80 cm circulars; sets of 5 dpn

CROCHET HOOK: U. S. size E-4 / 3.5 mm

GAUGE

Approx. 21 sts x 27 rnds on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

Edge Stitches: The two outermost sts at each side of the placket are worked as an I-cord: do not knit/purl the edge sts on WS; instead slip those sts; knit the edge sts on RS.

Pm: place markers onto the needle between 2 sts.

M1L (make 1 left): With left needle, pick up the strand between 2 stitches from front to back and knit into back loop.

M1R (make 1 right): With left needle, pick up the strand between 2 stitches from back to front and knit into front loop.

BEGIN WITH NECKBAND

With color A and larger size circular, CO 50 (68, 66, 72 80) sts. The 1st row = RS. Working back and forth, knit 1 row, purl 1 row.

RAGLAN SHAPING

Pm as you knit across row: K8 (10, 12, 13, 16)–front, pm; k10–sleeve, pm; k14 (18, 22, 26, 28)–back, pm; k10–sleeve, pm; k8 (10, 12, 13, 16)–front.

Work back and forth in stockinette with 2 I-cord sts at each side.

Increase 1 st on each side of st before/after each marker on every other row (= every RS row): M1L, k1, sl m, k1, M1R.

So, *knit until 1 st before marker, M1L, k1, sl m, k1, M1R*; rep * to * at each marker. Knit to end of row.

Increase on every other row a total of 10 (10, 11, 11, 12) times = 130 (138, 154, 160, 176) sts.

Now join to work in the round, beginning on RS:

Knit to last 2 sts of row. Place these 2 sts on a holder, hold them behind the first 2 sts of row, and knit the 2 sets of sts together = 128 (136, 152, 158, 174) sts.

Now begin knitting in the round, working raglan increases on alternate rnds a total of 14 (15, 16, 17, 18) times = 160 (176, 192, 206, 222) sts.

DIVIDE FOR BODY AND SLEEVES

Knit to first marker. Place the 38 (40, 42, 44, 46) sleeve sts on a holder and CO 6 new sts for underarm. Knit to second sleeve, set aside its sts, and CO 6 underarm sts = 96 (108, 120, 130, 142) sts rem for body.

The rnd now begins at left sleeve.

Count out 12 (13, 15, 16, 17) sts in each direction from center of each underarm and pm at each side = 4 markers placed.

Knit around for $\frac{3}{4}$ (1 $\frac{1}{4}$, 1 $\frac{1}{4}$, 1 $\frac{1}{2}$, 1 $\frac{1}{2}$) in / 2 (3, 3, 4, 4) cm.

Increase on next rnd as for RAGLAN SHAPING.

Rep the raglan increases every 2 (2 $\frac{1}{2}$, 3 $\frac{1}{4}$, 2 $\frac{3}{4}$, 3 $\frac{1}{4}$) in / 5 (6, 8, 7, 8) cm a total of 3 (3, 3, 4, 4) times = 120 (132, 144, 162, 174) sts.

Continue around without increasing until tunic measures 7 $\frac{1}{2}$ (9, 10 $\frac{3}{4}$, 12 $\frac{3}{4}$, 14 $\frac{1}{2}$) in / 19 (23, 27, 32, 37) cm from underarms.

Now work lower edge pattern following chart, beginning at one side so the jog between rnds will be less visible. After completing pattern, work with color D only, changing to smaller size circular. Make 3 garter ridges: knit 1 rnd, purl 1 rnd, knit 1 rnd, purl 1 rnd, knit 1 rnd. BO purlwise.

SLEEVES

Each sleeve has 38 (40, 42, 44, 46) sts.

Divide sts of one sleeve onto larger size dpn; pick up and knit 6 sts along underarm = 44 (46, 48, 50, 52) sts. Pm at center of underarm sts. Knit around. Every 1 $\frac{3}{8}$ (1 $\frac{3}{8}$, 2 $\frac{1}{2}$, 2 $\frac{1}{2}$, 2) in / 3.5 (3.5, 6, 6, 5) cm, decrease on each side of marker a total of 4 (5, 3, 4, 5) times = 36 (36, 42, 42, 42) sts rem. Continue without decreasing until sleeve is 6 $\frac{1}{4}$ (7 $\frac{1}{2}$, 8 $\frac{3}{4}$, 9 $\frac{3}{4}$, 11) in / 16 (19, 22, 25, 28) cm long. Now work charted pattern once in length. After completing pattern, work with color D only, changing to smaller size dpn.

Make 3 garter ridges: knit 1 rnd, purl 1 rnd, knit 1 rnd, purl 1 rnd, knit 1 rnd. BO purlwise.

Make the second sleeve the same way.

TIE CORD

With color A, crochet a chain about 4 $\frac{3}{4}$ -6 in / 12-15 cm long. Turn and work 1 sl st in each ch. Continue working sl st around neck in the cast-on row. After crocheting around neck, ch for 4 $\frac{3}{4}$ -6 in / 12-15 cm long. Turn and work 1 sl st in each ch back to neckline.

FINISHING

Close any holes at underarms with a few stitches. Weave in all ends neatly on WS.

SCHEMATICS

A 19 (22 $\frac{1}{2}$, 24 $\frac{1}{2}$, 26 $\frac{1}{2}$) in / 48 (52, 57, 62, 67) cm

B 14 $\frac{1}{4}$ (16 $\frac{1}{4}$, 18 $\frac{1}{4}$, 20 $\frac{1}{2}$, 22 $\frac{1}{2}$) in / 36 (41, 46, 52, 57) cm

C 4 $\frac{1}{4}$ (4 $\frac{3}{4}$, 5, 5 $\frac{1}{2}$, 5 $\frac{1}{2}$) in / 11 (12, 13, 14, 14) cm

D 10 $\frac{1}{4}$ (11 $\frac{3}{4}$, 13 $\frac{1}{2}$, 15 $\frac{1}{2}$, 17 $\frac{1}{4}$) in / 26 (30, 34, 39, 44) cm


E 9 $\frac{1}{2}$ (11, 12 $\frac{1}{4}$, 13 $\frac{1}{2}$, 15) 24 (28, 31, 34, 38) cm

F 8 $\frac{1}{4}$ (8 $\frac{3}{4}$, 9, 9 $\frac{1}{2}$, 9 $\frac{3}{4}$) in / 21 (22, 23, 24, 25) cm


G 22 $\frac{1}{2}$ (24 $\frac{3}{4}$, 27 $\frac{1}{4}$, 30 $\frac{1}{4}$, 32 $\frac{3}{4}$) in / 57 (63, 69, 77, 83) cm

H 8 $\frac{1}{4}$ (9 $\frac{1}{2}$, 10 $\frac{3}{4}$, 11 $\frac{3}{4}$, 13) in / 21 (24, 27, 30, 33) cm

I 6 $\frac{3}{4}$ (6 $\frac{3}{4}$, 8, 8, 8) in / 17 (17, 20, 20, 20) cm



- Color A
- Color B
- Color C
- Color D



- | |
|---------------------------|
| A ≈ 48 (52) 57 (62) 67 cm |
| B ≈ 36 (41) 46 (52) 57 cm |
| C ≈ 11 (12) 13 (14) 14 cm |
| D ≈ 26 (30) 34 (39) 44 cm |
| E ≈ 24 (28) 31 (34) 38 cm |
| F ≈ 21 (22) 23 (24) 25 cm |
| G ≈ 57 (63) 69 (77) 83 cm |
| H ≈ 21 (24) 27 (30) 33 cm |
| I ≈ 17 (17) 20 (20) 20 cm |



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92627



Vidja - child's pants

Single-color pants with ribbing and cables. Knitted from the top down. It's easy to lengthen the legs.

LEVEL OF DIFFICULTY **

SIZES

6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

European sizes 74-80 (86-92, 98-104, 110-116, 122-128) CL

FINISHED MEASUREMENTS

Circumference, hip: approx. 21¾ (22¾, 24¾, 26¾, 28¾) in / 55 (58, 63, 68, 73) cm

Total Length: approx. 18 (21, 23¾, 26½, 29¾) in / 45.5 (52.5, 60.5, 67.5, 75.5) cm

Inner Leg length: approx. 10¾ (13, 15¾, 18¼, 21) in / 27 (33, 40, 46, 53) cm

YARN CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Mellanraggi (75% wool, 25% polyamide, 284 yd/260 m / 100g)

CYCA #3 (DK, light worsted), Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Lady (100% acrylic, 138 yd/126 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Svensk Ull (100% Swedish wool, 197 yd/180 m / 100 g)

YARN COLOR AND AMOUNTS Tobacco Brown 18404: approx. 130 (150, 180, 200, 230) g

NOTIONS 6 stitch markers

NEEDLES U. S. sizes 4 and 6 / 3.5 and 4 mm: 16 and 24 in / 40 and 60 cm circulars, sets of 5 dpn; cable needle

GAUGE

Approx. 24 sts x 30 rows/rnds in slightly stretched k2, p2 ribbing on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

Right Twist Cable: Place 2 knit sts and 2 purl sts on cable needle and hold behind work, k2, slip 2 purl sts from cable onto left needle, p2, k2 from cable needle.

Left Twist Cable: Place 2 knit sts and 2 purl sts on cable needle and hold in front of work, k2, slip 2 purl sts from cable onto left needle, p2, k2 from cable needle.

Pm: place markers onto the needle between 2 sts.

M1L (make 1 left): With left needle, pick up the strand between 2 stitches from front to back and knit into back loop.

M1R (make 1 right): With left needle, pick up the strand between 2 stitches from back to front and knit into front loop.

BEGIN AT WAIST

With smaller size circular, CO 99 (105, 114, 123, 132) sts loosely. Join, being careful not to twist cast-on row; pm for beginning of rnd. Work around in (k1, p1, k1) ribbing for 1 (1, 1¼, 1¼, 1¼) in / 2.5 (2.5, 3, 3, 3) cm.

Make an eyelet rnd: (K1, yo, p1, k1) around = 132 (140, 152, 164, 176) sts.

Pm 1 at beginning of rnd = center back.

Pm 2 after 23 (23, 27, 31, 35) sts.

Pm 3 after 22 sts = cable.

Pm 4 after 21 (25, 27, 29, 31) sts.

Pm 5 after 21 (25, 27, 29, 31) sts.

Pm 6 after 22 sts = cable.

Knit to end of row = K23 (23, 27, 31, 35).

Change to larger size circular and work 1 rnd with knit over knit and purl over purl. purling all yarnovers.

RAISING BACK

Work with knit over knit and purl over purl as you work short rows to raise the back. For invisible turns, we recommend the German short row method (see sock pattern on page 19 for how to work German short rows).

Work until 6 sts past Marker 1; turn. Work 6 sts past Marker 1. Turn and work 8 sts past previous turn. Continue turning with 8 sts more on every turn until you've turned a total of 6 times on each side of Marker 1.

Now resume working in the round with knit over knit and purl over purl and the cable pattern following chart between Markers 2 and 3, as well as between Markers 5 and 6 until piece measures 6¼ (6¾, 7, 7½, 8) in / 16 (17, 18, 19, 20) cm. at center front.

CROTCH GUSSETS

Now work the crotch gussets at Markers 1 and 4. Knit all the new gusset sts. Increase *on every other rnd* as follows:

Rnd 1: MIL, k1, sl m, k1, M1R.

Rnd 3: MIL, k2, sl m, k2, M1R.

Rnd 5: MIL, k3, sl m, k3, M1R.

Rnd 7: MIL, k4, sl m, k4, M1R.

= 148 (156, 168, 180, 192) sts.

Now divide body for legs.

LEGS

Place half the sts on a holder, from Marker 1 to Marker 4 = 74 (78, 84, 90, 96) sts for each leg.

Place Marker 1 at center of crotch and knit around rem sts, with knit over knit and purl over purl and cable sts as est.

Decrease 1 st on each side of Marker 1 about every 3/8 (5/8, ¾, ¾, 1) in / 1 (1.5, 2, 2, 2.5) cm a total of 15 (15, 16, 17, 18) times = 44 (48, 52, 56, 60) sts rem.

Continue without decreasing until leg measures 8¾ (11, 13½, 15¾, 18¼) in / 22 (28, 34, 40, 46) cm.

Change to smaller size dpn, complete cable pattern and continue with knit over knit and purl over purl for 2 (2, 2½, 2½, 2¾) in / 5 (5, 6, 6, 7) cm. BO loosely with knit over knit and purl over purl.

Make the second leg the same way.

FINISHING

Seam crotch. Weave in all ends neatly on WS.

SCHEMATICS

A 16¼ (17¼, 19, 20, 21¾) in / 41 (44, 48, 51, 55) cm

B 21¾ (22¾, 24¾, 26¾, 28¾) in / 55 (58, 63, 68, 73) cm




C 18¼ (21, 24, 26¾, 30) in / 46 (53, 61, 68, 76) cm

D 8 (8¾, 9, 9¾, 10¼) in / 18 (20, 22, 23, 25) cm

E 10¾ (13, 15¾, 18¼, 21) in / 27 (33, 40, 46, 53) cm

F 7½ (8, 8¼, 8¾, 9) in / 19 (20, 21, 22, 23) cm

G 12¼ (13, 13¾, 15, 15¾) in / 31 (33, 35, 38, 40) cm



A	≈ 41 (44) 48 (51) 55 cm
B	≈ 55 (58) 63 (68) 73 cm
C	≈ 46 (53) 61 (68) 76 cm
D	≈ 18 (20) 22 (23) 25 cm
E	≈ 27 (33) 40 (46) 53 cm
F	≈ 19 (20) 21 (22) 23 cm
G	≈ 31 (33) 35 (38) 40 cm

Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92631



Vidja - child's socks

Toe-up cable-pattern socks beginning with Judy's Magic Cast-on, German short row heels and an elastic bind-off make these socks perfect for learning several new techniques.

LEVEL OF DIFFICULTY **

SIZES

6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

European 18-20 (21-23, 24-26, 27-29, 30-32)

FINISHED MEASUREMENTS

Sock Length: approx. 5¼ (6, 6¼, 7½, 8¼) in / 13 (15, 16, 19, 21) cm

YARN CYCA #2 (sport), Mellanraggi (75% Merino wool, 25% polyamide, 304 yd/278 m / 100g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Merino Raggi (100% superwash wool, 137 yd/125 m / 50 g)

CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

CYCA #3 (DK, light worsted), Nya Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

YARN COLOR AND AMOUNTS Pacific 28233: approx. 35 (40, 45, 50, 55) g

NEEDLES U. S. size 2.5 / 3 mm: 24-32 in / 60-80 circular for Magic Loop (or 2 circulars if you prefer that method); cable needle

GAUGE

Approx. 24 sts x 27 rnds in stockinette = 4 x 4 in / 10 x 10 cm.

Approx. 34 sts x 27 rnds in ribbing when slightly stretched = 4 x 4 in / 10 x 10 cm.

Adjust needle size to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

Judy's Magic Cast-on: Use either 2 circular needles or both tips of 1 circular (Magic Loop). Hold both tips together in your right hand, with the tips pointed towards the left. Hold the yarn in your left hand as for long-tail cast-on, with the tail end over your thumb and the ball end over your forefinger. Begin by laying the yarn over the needle nearest you. *Lay thumb yarn over the back needle so that it comes up between the needles and goes over the needle. Lay the forefinger yarn over the nearest needle, from the front and then down between the needles.* Rep * to * until you've cast on the desired number of sts. The top side is the RS (right side).

Video (Judy's Magic Cast-on): <https://youtu.be/y7MZPq928yM>.

Right Twist Cable: Place 1 knit st and 1 purl st on cable needle and hold behind work, k1, slip 1 purl st from cable onto left needle, p1, k1 from cable needle.

Left Twist Cable: Place 1 knit st and 1 purl st on cable needle and hold in front of work, k1, slip 1 purl st from cable onto left needle, p1, k1 from cable needle.

BEGIN AT TOE

CO 10 sts with Judy's Magic Cast-on (double cast-on) = 5 sts on each needle. Knit around the sts on both needles and, *at the same time*, on every rnd, increase 1 st on each side by working kf&b into the first and last st on each needle. Increase the same way a total of 4 (4, 4, 5, 5) times = 26 (26, 26, 30, 30) sts. Now increase on every other rnd 3 (4, 4, 4, 4) times = 38 (42, 42, 46, 46) sts. Knit 1 rnd. Now work in k1, p1 ribbing on instep; rnd ends with p1. Work sole sts in stockinette.

Continue around with ribbing on instep and stockinette on sole until piece measures 3¼ (4¼, 4½, 5¼, 6¼) in / 9.5 (10.5, 11.5, 13.5, 15.5) cm.

HEEL

Work heel over half the sts with German short rows. Turn work so WS faces and yarn is in front towards you. Sl 1 purlwise wyf, pull yarn up firmly over right needle so you flip st and have 2 stitch legs or a double stitch (DS) on the needle; purl rem sts on needle.

Turn work with RS facing and yarn in front, Sl 1, pull yarn up firmly over right needle for double stitch on the needle; knit rem sts up to DS at other end of needle.

Continue working back and forth the same way until 9 sts rem at the center of the needle and 5 (6, 6, 7, 7) DS on each side.

Now you will join the double sts one at a time. With RS facing, knit to the 1st DS, knit it, catching both legs of DS to make 1 st.

Turn, sl 1st st and purl to the next DS and purl both legs of DS together.

Turn and sl 1st st.

Continue back and forth in stockinette until all the double sts have been worked and 19 (21, 21, 23, 23) sts rem on needle.

When the heel is finished, return to knitting in the round over all sts on both needles. On the first rnd, pick up and knit 1 st on each side of heel, in the space between heel and instep. Knit the new st together with the next st to avoid a hole. Knit 3 rnds with stockinette on sole and ribbing on instep and then work 1 rnd k1, p1 ribbing over all sts.

Set up to work cable pattern on each side of sock leg. The cable pattern has 11 sts. The first and last purl st on instep needle is the center st of chart on each side. Count out 5 sts on each side of this center st and mark if necessary. The rnd begins and ends at center back. Rep the chart rows 2 (2, 2, 3, 3) times in length or to desired length. End with chart row 1 and then BO.

Elastic Bind-off:

P1, yo, k1, pass purl st and yo over knit st. Yo, p1, pass knit st and yo over purl st.

Continue as est with a yarnover between each st and with knit over knit and purl over purl around.

Make the second sock the same way.


SCHEMATICS

A 5¼ (6, 6¼, 7¼, 8) in / 13.2 (14.9, 15.9, 18.7, 20.7) cm


B 5¼ (6, 6, 6¼, 6 ¼) in / 13.5 (14.9, 14.9, 16.3, 16.3) cm

C 3¾ (3¾, 3¾, 5½, 5½) in / 9.6 (9.6, 9.6, 14.1, 14.1) cm

D 4¼ (5, 5, 5¼, 5¼) in / 11.2 (12.4, 12.4, 13.5, 13.5) cm



- Knit
- Purl
- Left Twist Cable
- Right Twist Cable



A	≈ 13,2	(14,9)	15,9	(18,7)	20,7	cm
B	≈ 13,5	(14,9)	14,9	(16,3)	16,3	cm
C	≈ 9,6	(9,6)	9,6	(14,1)	14,1	cm
D	≈ 11,2	(12,4)	12,4	(13,5)	13,5	cm



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92632



Tjörn - child's mittens

The right and left mittens are knitted the same way so it's easier for the little ones to put them on themselves.

LEVEL OF DIFFICULTY *

SIZES 6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

FINISHED MEASUREMENTS

Circumference, hand approx. 4¾ (5½, 6¼, 6¼, 6¾) in / 12 (14, 15.5, 15.5, 17) cm

Length, hand: approx. 4 (4¼, 4¾, 5¼, 5½) in / 10 (11, 12, 13, 14) cm

YARN CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Mellanraggi (75% wool, 25% polyamide, 284 yd/260 m / 100g)

CYCA #3 (DK, light worsted), Nya Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Lady (100% acrylic, 138 yd/126 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Svensk Ull (100% Swedish wool, 197 yd/180 m / 100 g)

YARN COLORS AND AMOUNTS

Color A: Natural White 18402: approx. 25 (30, 35, 40, 45) g

Color B: Dark Teal 18417: less than 10 (10, 10, 10, 10) g

Color C: Tobacco Brown 18404: less than 5 (5, 5, 5, 5) g

NEEDLES U. S. sizes 2.5 and 4 / 3 and 3.5: sets of 5 dpn

GAUGE

Approx. 23 sts x 30 rnds on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

M1L (make 1 left): With left needle, pick up the strand between 2 stitches from front to back and knit into back loop.

M1R (make 1 right): With left needle, pick up the strand between 2 stitches from back to front and knit into front loop.

BEGIN WITH CUFFS

With color B and larger size dpn, CO 28 (32, 36, 36, 40) sts.

Arrange sts so the WS of the cast-on row is on RS. Divide sts onto dpn and join. Work around in garter st: Alternate knit 1 rnd, purl 1 rnd until there are 3 purl ridges. End with knit 1 rnd.

Now work in pattern following chart, working rep once in length.

With color A, knit around until piece is 2 (2½, 2, 3, 3¼) in / 5 (6, 7, 8, 8.5) cm long.

Change to smaller size dpn and work in k1, p1 ribbing for ¾ in / 2 cm.

Change back to larger size dpn and knit 1 rnd.

THUMB GUSSET

At beginning of next rnd: M1L, k3, M1R = thumb gusset; knit to end of rnd.

Knit 2 rnds.

On every 3rd rnd, increase as before, with 2 more sts between increases each time, a total of 2 (3, 4, 4, 5) times.

When stockinette section is 1 (1¼, 1 ¾, 1½, 1¾) in / 2.5 (3, 3.5, 4, 4.5) cm long, place the first 7 (9, 11, 11, 13) sts on a holder.

CO 3 new sts over gap and continue knitting in the round = 28 (32, 36, 36, 40) sts.

Continue in stockinette until mitten is 3¼ (3½, 4, 4¼, 4¾) in / 8 (9, 10, 11, 12) cm above ribbing.

Top shaping:

Decrease Rnd 1: *K2, k2tog*; rep * to * around = 21 (24, 27, 27, 30) sts rem.

Knit 1 rnd.

Decrease Rnd 2: *K1, k2tog*; rep * to * around = 14 (16, 18, 18, 20) sts rem.

Knit 1 rnd.

Decrease Rnd 3: K2tog around = 7 (8, 9, 9, 10) sts rem.

Knit 1 rnd.

Cut yarn and draw end through rem sts; tighten.

THUMB

With color A and larger size dpn, divide the 7 (9, 11, 11, 13) held sts on dpn and pick up and knit 3 sts along top of thumbhole = 10 (12, 14, 14, 16) sts.

Knit around in stockinette for 1¼ (1 3/8, 1½, 1¾, 2) in 3 (3.5, 4, 4.5, 5) cm.

K2tog around = 5 (6, 7, 7, 8) sts rem.

Cut yarn and draw end through rem sts; tighten.

Weave in all ends neatly on WS.


SCHEMATICS

A 6¾ (7½, 8¼, 9, 9½) in / 17 (19, 21, 23, 24.5) cm

B 4¾ (5½, 6¼, 6¾, 6¾) in / 12.2 (13.9, 15.7, 15.7, 17.4) cm

C 3 (3¼, 3¼, 3½, 3¾) in / 7.5 (8, 8.5, 9, 9.5) cm

D 1¼ (1 3/8, 1½, 1¾, 2) in / 3 (3.5, 4, 4.5, 5) cm



A ≈ 17,0 (19,0) 21,0 (23,0) 24,5 cm
 B ≈ 12,2 (13,9) 15,7 (15,7) 17,4 cm
 C ≈ 7,5 (8,0) 8,5 (9,0) 9,5 cm
 D ≈ 3,0 (3,5) 4,0 (4,5) 5,0 cm



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92636



Töre - child's cap

This cap with an upturned brim is worked from the bottom up.

LEVEL OF DIFFICULTY **

SIZES 2-6 (8-14) years

FINISHED MEASUREMENTS

Circumference: approx. 17 (20) in / 43 (51) cm

YARN CYCA #2 (sport), 2 tr ull 2 (2-Ply Wool) (100% wool, 328 yd/300 m / 100 g)

ALTERNATE YARN SUGGESTIONS:

CYCA #2 (sport), Alpaca Solo (100% alpaca, 183 yd/167 m / 50 g)

CYCA #2 (sport), Elise (60% cotton, 40% acrylic, 184 yd/168 m / 50 g)

CYCA #1 (fingering), Junior (70% acrylic, 30% nylon, 184 yd/168 m / 50 g)

CYCA #2 (sport), Ístex Kambgarn (100% Merino wool, 164 yd/150 m / 50 g)

YARN COLORS AND AMOUNTS

Color A: Sandy 74110: approx. 10 (15) g

Color B: Almond 74111: approx. 30 (40) g

Color C: Copper Blush 74120: less than 5 (5) g

NEEDLES

U.S. size 2.5 / 3 mm: 16 in / 40 mm circular;

U.S. size 4 / 3.5 mm: 16 in / 40 cm circular; set of 5 dpn

GAUGE

Approx. 21 sts x 23 rnds on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

K2tog: right-leaning decrease

Ssk: left-leaning decrease = (sl 1 knitwise) 2 times, place st back on left needle and knit together through back loops.

CAP

With smaller size circular and color B, CO 90 (108) sts. Join, being careful not to twist cast-on row; pm for beginning of rnd. Work around in k1, p1 ribbing for 4¼ (6¼) in / 11 (16) cm.

Change to larger size circular (change to dpn when sts no longer fit around circular).

Work in pattern following chart. Always work decreases with color A.

Cut yarn and draw color A end through rem sts; tighten.


Weave in all ends neatly on WS.

SCHEMATICS


A 17 (20) in / 43 (51) cm

B 9¾ (11¾) in / 25 (30) cm

C 8 (8¾) in / 20 (22) cm



- Color A
- Color B
- Color C
- / Ssk
- \ K2tog
- X No stitch, skip over



A ≈ 43 (51) cm
 B ≈ 25 (30) cm
 C ≈ 20 (22) cm

Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92626



Tjörn - Child's Cardigan

A classic cardigan knitted in the round from the top down before it is cut open down the steek.

LEVEL OF DIFFICULTY ***

SIZES

6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

Sizes 6-12 months (24 months, 4T, 6, 7-8) / European sizes 74-80 (86-92, 98-104, 110-116, 122-128) CL

FINISHED MEASUREMENTS

Chest: approx. 21¾ (22¾, 24¾, 27¼, 29½) in / 55 (58, 63, 69, 75) cm

Total Length: approx. 13¾ (15, 15¾, 18¼, 19¾) in / 35 (38, 40, 46, 50) cm

Sleeve length: approx. 8¾ (9½, 10¾, 11¾, 13) in / 22 (24, 27, 30, 33) cm

YARN CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Mellanraggi (75% wool, 25% polyamide, 284 yd/260 m / 100g)

CYCA #3 (DK, light worsted), Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Lady (100% acrylic, 138 yd/126 m / 50 g)

YARN COLORS AND AMOUNTS

Color A: Dark Teal 18417: approx. 70 (80, 90, 115, 140) g

Color B: Tobacco Brown 18404: approx. 60 (60, 60, 70, 70) g

Color C: Heather Beige 18405: approx. 15 (15, 15, 20, 20) g

Color D: Natural White 18402: approx. 40 (50, 50, 60, 60) g

NEEDLES U. S. sizes 4 and 6 / 3.5 and 4 mm: 24-32 in / 60-80 cm circulars and sets of 5 dpn

NOTIONS 6 (7, 8, 9, 10) buttons

GAUGE

Approx. 21 sts x 27 rnds on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

M1L (make 1 left): With left needle, pick up the strand between 2 stitches from front to back and knit into back loop.

M1R (make 1 right): With left needle, pick up the strand between 2 stitches from back to front and knit into front loop.

Buttonholes: yo, k/p2tog (knit or purl as est in pattern).

BEGIN AT NECKLINE

With color B and larger size circular, CO 66 (70, 74, 83, 86) sts. Do not join.

Set up steek: p2, k1, p2, knit to end of row The first 5 sts are the steek (extra sts to be cut open later for center front). Throughout, work the 5 steek sts as (p2, k1, p2). Join; pm for beginning of rnd. Following chart, work around in pattern, increasing as indicated on Yoke chart. The repeats + 1 extra st makes the pattern symmetrical on both front pieces. The last st is worked as the first.

After completing yoke, there are 181 (193, 205, 229, 241) sts + 5 steek sts.

DIVIDE FOR BODY AND SLEEVES

When piece measures approx. 4¼ (4, 5¼, 5, 6) in / 11 (12, 13, 14, 15) cm, set aside sts for sleeves as follows: Work 5 steek sts, k24 (26, 29, 31, 34). Place the next 42 (45, 45, 51, 51) sts on a holder.

With backwards loop cast-on method, CO 6 new sts for underarm. K49 (51, 57, 65, 71).

Place the next 42 (45, 45, 51, 51) sts on a holder and CO 6 new sts, knit to end of rnd = 109 (115, 127, 139, 151) sts + 5 steek sts for body. On next rnd, knit each underarm st as k1tbl.

Pm at each side, centered at each underarm. Continue working around until body measures approx. 5¼ (6, 7, 8¼, 9½) in / 13 (15, 18, 21, 24) cm from underarm. Now work lower edge pattern following the Lower Edge Panel chart once in length.

RIBBED LOWER EDGE

There should now be 109 (115, 127, 139, 151) sts + 5 steek sts.

Change to smaller size circular and color B. Knit 1 rnd, binding off steek sts.

Work back and forth in k1, p1 ribbing for 1¼ in / 3 cm. BO in ribbing.

SLEEVES

There are 42 (45, 45, 51, 51) sts for each sleeve.

Place sts of one sleeve onto larger size dpn. Pick up and knit 6 sts in the sts cast-on for underarm = 48 (51, 51, 57, 57) sts. Pm at center of the 6 underarm sts. Now begin working in the round.

Every 1¼ (1¼, 1 3/8, 1½, 1¾) in / 3 (3, 3.5, 4, 4.5) cm, decrease 1 st on each side of marker 3 (4, 4, 4, 4) times = 42 (43, 43, 49, 49) sts rem.

When sleeve is approx. 5¼ (6, 7, 8¼, 9½) in / 13 (15, 18, 21, 24) cm long, k2tog at beginning of rnd 0 (1, 1, 1, 1) time so the stitch count will be a multiple of 6. Now work lower edge pattern following the Lower Edge Panel chart once in length.

Change to smaller size dpn and color B and knit 1 rnd. Work around in k1, p1 ribbing for 1½ in / 4 cm. BO in ribbing.

Make the second sleeve the same way.

FRONT BANDS

With RS facing, smaller size circular, and color B, beginning at lower edge of ribbing, pick up and knit 3 sts for every 4 rows along front edge to neck. Work back and forth in k1, p1 ribbing for 1¼ in / 3 cm. BO in ribbing.

Work opposite side the same way (beginning at neck), but, when the band is 5/8 in / 1.5 cm wide, make buttonholes. Place the first buttonhole about 5/8 in / 1.5 cm from lower edge and then space rem buttonholes approx. 2½ in / 6 cm apart. Continue in ribbing until band is 1¼ in / 3 cm wide; BO in ribbing.

NECKBAND

With smaller size circular and color B, pick up and knit 71 (75, 79, 87, 91) sts around neck. Work back and forth in k1, p1 ribbing for 5/8 in / 1.5 cm. Make a buttonhole on the next row, placing it directly over the other buttonholes on the front band. Continue in ribbing until neckband is approx. 1¼ in / 3 cm high. BO in ribbing.

FINISHING

Weave in all ends neatly on WS. Machine-stitch with short sts over the purl sts of steek, working 1 straight and 1 zigzag row on each side of center st. Carefully cut steek open up center knit st.

FACING FOR FRONT BANDS

With smaller size circular and color B, pick up and knit sts along back of front band. Work back and forth in stockinette for approx. 5/8 in / 1.5 cm. BO. Sew down facing to cover cut steek edge.

SCHEMATICS

A 21¾ (22¾, 24¾, 27¼, 29½) in / 55 (58, 63, 69, 75) cm

B 13¾ (15, 15¾, 18¼, 19¾) in / 35 (38, 40, 46, 50) cm

C 4¼ (4¾, 5¼, 5, 6) in / 11 (12, 13, 14, 15) cm

D 8¾ (9½, 10¾, 11¾, 13) in / 22 (24, 27, 30, 33) cm


E 12¾ (13½, 14¼, 15¾, 16½) in / 32 (34, 36, 40, 42) cm

F 9 (9½, 9½, 10¾, 10¾) in / 23 (24, 24, 27, 27) cm

G 8¾ (9½, 10¾, 11¾, 13) in / 22 (24, 27, 30, 33) cm



H 8 (8, 8, 8¾, 8¾) in / 20 (20, 20, 22, 22) cm

YOKE



- Color A
- Color B
- Color C
- Color D
- No st, skip to next square
- MH M1R
- MV M1L

LOWER EDGE PANEL



- A ≈ 55 (58) 63 (69) 75 cm
- B ≈ 35 (38) 40 (46) 50 cm
- C ≈ 11 (12) 13 (14) 15 cm
- D ≈ 22 (24) 27 (30) 33 cm
- E ≈ 32 (34) 36 (40) 42 cm
- F ≈ 23 (24) 24 (27) 27 cm
- G ≈ 22 (24) 27 (30) 33 cm
- H ≈ 20 (20) 20 (22) 22 cm



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92634



Töre - child's pullover

Here's a classic sporty pullover with a doubled neckband and a timeless pattern on the round yoke. The sleeve cuffs fold up double so the sweater grows with the child. It is knitted in the round from the top down with a long body and sleeves that can be easily lengthened or shortened.

LEVEL OF DIFFICULTY **

SIZES

2-4 (4-6, 6-8, 8-10, 10-12, 12-14) years

European sizes 98-104 (110-116, 122-128, 134-140, 146-152, 158-164) CL

FINISHED MEASUREMENTS

Chest: approx. 26½ (27½, 29¼, 31½, 34, 36) in / 67 (70, 74, 80, 86, 91) cm

Total Length: approx. 18¼ (20, 21¾, 23¾, 24¾, 26½) in / 46 (51, 55, 60, 63, 67) cm with doubled neckband

Sleeve length: approx. 10¼ (11½, 13, 14¼, 15¾, 16½) in / 26 (29, 33, 36, 40, 42) cm with doubled cuff

YARN CYCA #2 (sport), 2 tr ull (2-Ply Wool) (100% wool, 328 yd/300 m / 100 g)

ALTERNATE YARN SUGGESTIONS:

CYCA #2 (sport), Alpaca Solo (100% alpaca, 183 yd/167 m / 50 g)

CYCA #2 (sport), Elise (60% cotton, 40% acrylic, 184 yd/168 m / 50 g)

CYCA #1 (fingering), Junior (70% acrylic, 30% nylon, 184 yd/168 m / 50 g)

CYCA #2 (sport), Ístex Kambgarn (100% Merino wool, 164 yd/150 m / 50 g)

YARN COLORS AND AMOUNTS

Color A: Sandy 74110: approx. 120 (150, 180, 210, 250, 300) g

Color B: Almond 74111: approx. 50 (50, 60, 70, 80, 90) g

Color C: Copper Blush 74120: approx. 5 (5, 5, 5, 5, 5) g

NEEDLES

U. S. size 2.5 / 3 mm: 16 and 24 in / 40 and 60 mm circulars; set of 5 dpn

U. S. size 4 / 3.5 mm: 24/32 in / 60/80 cm circular; set of 5 dpn

GAUGE

Approx. 21 sts x 23 rnds on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

M1L (make 1 left): With left needle, pick up the strand between 2 stitches from front to back and knit into back loop.

M1R (make 1 right): With left needle, pick up the strand between 2 stitches from back to front and knit into front loop.

BEGIN WITH NECKBAND

With color B and smaller size circular, CO 72 (78, 84, 90, 96, 102) sts. Join, being careful not to twist cast-on row; pm for beginning of rnd. Work around in k1, p1 ribbing for 4 (4¾, 4¾, 5½, 5½, 6¼) in / 10 (12, 12, 14, 14, 16) cm.

Change to larger size circular and BO knitwise. Do not cut yarn but use it to pick up and knit all the sts again – this prevents the neckband from sliding down the shoulders.

YOKE

Work in pattern and shape yoke following YOKE chart. After completing increases, there should be 216 (234, 252, 270, 288, 306) sts.

Continue with color A only.

After the ribbing, when body measures 4¾ (5¼, 5½, 6, 6¼, 6¾) in / 12 (13, 14, 15, 16, 17) cm, divide for body and sleeves.

DIVIDE FOR BODY AND SLEEVES

Place the first 44 (49, 54, 57, 60, 63) sts on a holder and CO 6 new sts. K64 (68, 72, 78, 84, 90), place the following 44 (49, 54, 57, 60, 63) sts on a holder and CO 6 new sts. K64 (68, 72, 78, 84, 90). Body = 140 (148, 156, 168, 180, 192) sts.

Continue working in the round until body measures 7½ (8¾, 9¾, 10¾, 11½, 12¼) in / 19 (22, 25, 27, 29, 31) cm from underarms. Now work in pattern following chart LOWER EDGE PANEL once in length.

Ribbing:

Change to smaller size circular and color B. Work around in k1, p1 ribbing for 1½ (1½, 2, 2, 2½, 2½) in / 4 (4, 5, 5, 6, 6) cm. BO in ribbing.

SLEEVES

Place the 44 (49, 54, 57, 60, 63) held sleeve sts on larger size dpn. Pick up the 6 cast-on sts at underarm and pm at center of underarm = 50 (55, 60, 63, 66, 69) sts. With color A, knit around, decreasing 1 st on each side of marker every 1½ (1½, 1½, 1½, 1 3/8, 1½) in / 4 (4, 4, 4, 3.5, 4) cm a total of 5 (5, 6, 7, 8, 9) times = 40 (45, 48, 49, 48, 53) sts rem.

Knit until sleeve is 7½ (8¾, 9¾, 11, 12¼, 13) in / 19 (22, 25, 28, 31, 33) cm long or desired length.

Adjust stitch count with 0 (-1, 0, -1, 0, -1) st so 40 (44, 48, 48, 48, 52) sts rem. Now work in pattern following chart LOWER EDGE PANEL once in length.

Ribbing:

Change to smaller size dpn and color B. Work around in k1, p1 ribbing for 3¼ (3¼, 4, 4, 4¾, 4¾) in / 8 (8, 10, 10, 12, 12) cm. BO in ribbing.

Make the second sleeve the same way.

SCHEMATICS

A 26½ (27½, 29¼, 31½, 34, 36) in / 67 (70, 74, 80, 86, 91) cm

B 18¼ (20, 21¾, 23¾, 24¾, 26½) in / 46 (51, 55, 60, 63, 67) cm

C 4¾ (5¼, 5½, 6, 6¼, 6¾) in / 12 (13, 14, 15, 16, 17) cm

D 9¾ (11, 12¼, 13½, 14¼, XX) in / 25 (28, 31, 34, 36, 38) cm


E 13½ (14½, 15¾, 17, 18¼, XX) in / 34 (37, 40, 43, 46, 49) cm

F 9½ (10¼, 11½, 11¾, 12¼, XX) in / 24 (26, 29, 30, 31, 33) cm


G 10¼ (11½, 13, 14¼, 15¾, XX) in / 26 (29, 33, 36, 40, 42) cm

H 7½ (8¼, 9, 9, 9, X) in / 19 (21, 23, 23, 23, 25) cm


YOKE



LOWER EDGE PANEL



- Color A
- Color B
- Color C
- No st, skip over
- MH M1R
- MV M1L



- A ≈ 67 (70) 74 (80) 86 (91) cm
- B ≈ 46 (51) 55 (60) 63 (67) cm
- C ≈ 12 (13) 14 (15) 16 (17) cm
- D ≈ 25 (28) 31 (34) 36 (38) cm
- E ≈ 34 (37) 40 (43) 46 (49) cm
- F ≈ 24 (26) 29 (30) 31 (33) cm
- G ≈ 26 (29) 33 (36) 40 (42) cm
- H ≈ 19 (21) 23 (23) 23 (25) cm



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92635



Töre - child's mittens

Pretty mittens with size determined by the needle size and gauge.

LEVEL OF DIFFICULTY **

SIZES 2-4 (4-6, 6-8, 8-10, 10-12, 12-14) years

FINISHED MEASUREMENTS

Circumference: approx. 5½ (6, 6¼, 6¾, 7½, 8) in / 14 (15, 16, 17, 19, 20) cm

Length: approx. 5¼ (5½, 6, 6¼, 6¾, 7) in / 13 (14, 15, 16, 17, 18) cm

YARN CYCA #2 (sport), 2 tr ull (2-Ply Wool) (100% wool, 328 yd/300 m / 100 g)

ALTERNATE YARN SUGGESTIONS:

CYCA #2 (sport), Alpacka Solo (100% alpaca, 183 yd/167 m / 50 g)

CYCA #2 (sport), Elise (60% cotton, 40% acrylic, 184 yd/168 m / 50 g)

CYCA #1 (fingering), Junior (70% acrylic, 30% nylon, 184 yd/168 m / 50 g)

CYCA #2 (sport), Ístex Kambgarn (100% Merino wool, 164 yd/150 m / 50 g)

YARN COLORS AND AMOUNTS

Color A: Sandy 74110: approx. 15 (15, 15, 20, 20, 20) g

Color B: Almond 74111: approx. 20 (20, 25, 25, 30, 30) g

Color C: Copper Blush 74120: approx. 5 (5, 5, 5, 10, 10) g

NEEDLES U. S. sizes 0 (1, 1.5, 2, 2.5, 3 / 2 (2.25, 2.5, 2.75, 3, 3.25) mm: set of 5 dpn

GAUGE

Approx. 36 x 38 (34 x 36; 32 x 34; 30 x 32; 28 x 30; 26 x 38) sts x rnds = 4 x 4 in / 10 x 10 cm.

Adjust needle size to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

K2tog: right-leaning decrease

Ssk: left-leaning decrease = (sl 1 knitwise) 2 times, place st back on left needle and knit together through back loops.

Sk2p: Slip 1, knit 2 together, pass slipped st over = 2 sts decreased.

M1L (make 1 left): With left needle, pick up the strand between 2 stitches from front to back and knit into back loop.

M1R (make 1 right): With left needle, pick up the strand between 2 stitches from back to front and knit into front loop.

MITTENS

With color B and dpn for gauge for selected size, CO 44 sts. Divide sts onto dpn and join. Work around in k1, p1 ribbing for 1½ (1¾, 2, 2¼, 2 3/8, 2½) in / 4 (4.5, 5, 5.5, 6, 6.5) cm.

Knit 1 rnd.

Right-hand mitten: Work around, reading chart from right to left. Increase for thumb gusset as shown on chart. After completing gusset, place the 11 thumb sts on a holder. Continue in pattern, decreasing to shape top as shown. Cut yarn and draw end through rem sts; tighten.

Weave in all ends neatly on WS.

Left-hand mitten: Work around, reading chart from left to right. Increase for thumb gusset as shown on chart. After completing gusset, place the 11 thumb sts on a holder. Continue in pattern, decreasing to shape top as shown. Cut yarn and draw end through rem sts; tighten.

Weave in all ends neatly on WS.

THUMB

Divide held thumb sts onto dpn and work and shape thumb following chart, beginning rnd at front of thumb.

Cut yarn and draw end through rem sts; tighten.

Weave in all ends neatly on WS.

SCHEMATICS


A $6\frac{3}{4}$ ($7\frac{1}{4}$, $7\frac{3}{4}$, $8\frac{1}{4}$, 9, $9\frac{5}{8}$) in / (17.2 (18.4, 19.7, 21.1, 22.7, 24.4) cm

B $5\frac{1}{2}$ (6, $6\frac{1}{4}$, $6\frac{3}{4}$, $7\frac{1}{2}$, 8) in / 14 (15, 16, 17, 19, 20) cm

C $3\frac{1}{2}$ ($3\frac{3}{4}$, 4, $4\frac{1}{4}$, $4\frac{1}{2}$, $4\frac{3}{4}$) in / 8.9 (9.4, 10, 10.5, 11.3, 12.1) cm

D $1\frac{5}{8}$ ($1\frac{3}{4}$, $1\frac{3}{4}$, 2, $2\frac{1}{4}$, $2\frac{1}{2}$) in / 4.2 (4.4, 4.7, 5, 5.3, 5.7) cm

A ≈ 17,2 (18,4) 19,7 (21,1) 22,7 (24,4) cm
 B ≈ 14,0 (15,0) 16,0 (17,0) 19,0 (20,0) cm
 C ≈ 8,9 (9,4) 10,0 (10,6) 11,3 (12,1) cm
 D ≈ 4,2 (4,4) 4,7 (5,0) 5,3 (5,7) cm



Color A

Color B

Color C

Ssk

K2tog

Sk2p


MH M1R

MV M1L


Thumb gusset



MITTEN



THUMB



- Color A
- Color B
- Color C
- Ssk
- K2tog
- Sk2p
- M1R
- M1L
- Thumb gusset

Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over


CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92633



Tjörn - child's pants

Pants with an all-over pattern knitted from the top down.

LEVEL OF DIFFICULTY **

SIZES

6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

European sizes 74-80 (86-92, 98-104, 110-116, 122-128) CL

FINISHED MEASUREMENTS

Circumference, hip: approx. 20½ (22½, 24½, 26½, 28) in / 52 (57, 62, 67, 71) cm

Total Length: approx. 17¼ (20, 23¼, 26, 29¼) in / 44 (51, 59, 66, 74) cm

Inner Leg length: approx. 10¾ (13, 15¾, 18¼, 21) in / 27 (33, 40, 46, 53) cm

YARN CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Mellanraggi (75% wool, 25% polyamide, 284 yd/260 m / 100g)

CYCA #3 (DK, light worsted), Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Lady (100% acrylic, 138 yd/126 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Svensk Ull (100% Swedish wool, 197 yd/180 m / 100 g)

YARN COLORS AND AMOUNTS

Color A: Natural White 18402: approx. 50 (70, 80, 90, 100) g

Color B: Dark Teal 18417: approx. 30 (30, 40, 40, 50) g

Color C: Heather Beige 18405: approx. 50 (70, 80, 90, 100) g

NOTIONS waistband elastic, long enough to go around waist + 1 in / 2.5 cm for seaming

NEEDLES

U. S. size 4 / 3.5 mm: 16 and 24 in circulars, set of 5 dpn

U. S. size 6 / 4 mm: 16 in / 40 mm circular and set of 5 dpn

GAUGE

Approx. 21 sts x 23 rows/rnds on larger size needles = 4 x 4 in / 10 x 10 cm.

Adjust needle sizes to obtain correct gauge if necessary.

BEGIN AT WAIST

With smaller size circular and color B, CO 99 (108, 117, 126, 135) sts. Join, being careful not to twist cast-on row; pm for beginning of rnd. Knit around in stockinette for 1¼ (1¼, 1¼, 1½, 1½) in / 3 (3, 3, 4, 4) cm. Purl 1 rnd for foldline and then knit around for 1¼ (1¼, 1¼, 1½, 1½) in / 3 (3, 3, 4, 4) cm.

JOIN CASING

Fold the waistband at the purl rnd and join the live sts to the cast-on row: *K2tog joining next live st with corresponding st on cast-on row; rep from * around. If you find this too difficult, wait and sew the band facing down when finishing. Do try the knit join, though, as it looks very nice and isn't hard. Leave an opening in the casing so you can thread in the elastic later.

Change to larger size circular. Pm at center front and center back. Knit 1 rnd, increasing 1 st (with M1) after every 9th st = 110 (120, 130, 140, 150) sts.

RAISING BACK

Now raise the back by working back and forth, following the chart, RAISING BACK. Read the chart from the bottom up, from right to left on RS and left to right on WS. The symbol X on the chart means "no stitch," so just skip these squares on the chart.

Knit to marker at center back, k6; turn and sl 1st st. Purl to marker + 6 sts; turn, sl 1st st and knit to previous turn + 6 sts. Continue as est until you've completed all chart rows.

Now work in the round following chart, PATTERN. Knit around to raised back. Pm, the rnd begins and ends here. Knit following chart, making sure pattern stays aligned over the raised section. Continue until piece measures 5½ (6, 6¼, 6¼, 6) in / 14 (15, 16, 16, 17) cm at center front. Now work the crotch gussets at center front and center back.

CROTCH GUSSETS

You'll need to be careful and align the increases and pattern on each side of the gussets and then down over the legs.

Always check the previous rnd to make sure the pattern hasn't gone off track.

Increase on every other rnd for the gussets, at center front and center back, as indicated on the chart, CROTCH GUSSETS. Each gusset has 8 increases for a total of 16 sts increased = 126 (136, 146, 156, 166) sts. Cut yarn and divide for legs.

LEGS

Each leg has 63 (68, 73, 78, 83) sts.

Place half the sts, from marker to marker, on a holder or extra circular. Pm at center of crotch for beginning and end of rnd. Work pattern around, decreasing 1 st on each side of marker about every ¾ (¾, 1, 1, 1¼) in / 2 (2, 2.5, 2.5, 3) cm 10 (11, 12, 13, 14) times = a total of 43 (46, 49, 52, 55) sts rem. When leg is approx. 8¾ (11, 13½, 15¾, 18¼) in / 22 (28, 34, 40, 46) cm long or desired length, change to smaller size dpn and color B. Knit 1 rnd, *at the same time*, decreasing 1 (0, 1, 0, 1) st. Now work around in k1, p1 ribbing for 2 (2, 2½, 2½, 2¾) in / 5 (5, 6, 6, 7) cm.

BO in ribbing. Make the other leg the same way.

FINISHING

Seam crotch. Sew down casing if you haven't already joined it.

Weave in all ends neatly on WS. Thread waistband elastic through casing and seam ends; stitch casing to close.

SCHEMATICS

A 18½ (20, 22, 23¾, 25¼) in / 47 (51, 56, 60, 64) cm

B 20½ (22½, 24½, 26½, 28) in / 52 (57, 62, 67, 71) cm


C 17¼ (20, 23¼, 26, 29¼) in / 44 (51, 59, 66, 74) cm

D 8 (8¾, 9, 9¾, 10¼) in / 20 (22, 23, 25, 26) cm

E 10¾ (13, 15¾, 18¼, 21) in / 27 (33, 40, 46, 53) cm


F 8 (8, 8, 8, 8) in / 20 (20, 20, 20, 20) cm

G 11¾ (12¾, 13¾, 14½, 15¾) in / 30 (32, 35, 37, 40) cm




- A ≈ 47 (51) 56 (60) 64 cm
- B ≈ 52 (57) 62 (67) 71 cm
- C ≈ 44 (51) 59 (66) 74 cm
- D ≈ 20 (22) 23 (25) 26 cm
- E ≈ 27 (33) 40 (46) 53 cm
- F ≈ 20 (20) 20 (20) 20 cm
- G ≈ 30 (32) 35 (37) 40 cm

PATTERN




CROTCH GUSSETS



- Color A
- Color B
- No stitch
- MH M1R
- MV M1L

- Color A
- Color B
- No stitch



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over



JÄRBO

92630



Tjörn - child's cowl

A warm and lovely cowl knitted in the round from the top down. Long enough to warm the shoulders.

LEVEL OF DIFFICULTY **

SIZES

6-12 months (12-24 months, 2-4 years, 4-6 years, 6-8 years)

European sizes 74-80 (86-92, 98-104, 110-116, 122-128) CL

FINISHED MEASUREMENTS

Length: approx. 4¾ (4¾, 5, 5¼, 5½) in / 12 (12, 12.5, 13, 14) cm + ribbing

Circumference approx. 28 (30, 32, 34, 35½) in / 71 (76, 81, 86, 90) cm

YARN CYCA #3 (DK, light worsted), Astrid (100% superwash wool, 137 yd/125 m / 50 g)

ALTERNATE YARN SUGGESTIONS

CYCA #2 (sport), Mellanraggi (75% wool, 25% polyamide, 284 yd/260 m / 100g)

CYCA #3 (DK, light worsted), Nya Fuga (50% superwash wool, 50% acrylic, 126 yd/115 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Lady (100% acrylic, 138 yd/126 m / 50 g)

CYCA #4 (worsted. Afghan, Aran), Svensk Ull (100% Swedish wool, 197 yd/180 m / 100 g)

YARN COLORS AND AMOUNTS

Color A: Natural White 18402: approx. 25 (30, 30, 35, 40) g

Color B: Dark Teal 18417: approx. 25 (25, 25, 30, 35) g

Color C: Tobacco Brown 18404: approx. 20 (20, 20, 20, 25) g

NEEDLES U. S. size 6 / 4 mm: 16 and 24 in / 40 and 60 cm circulars

GAUGE

Approx. 21 sts x 27 rnds = 4 x 4 in / 10 x 10 cm.

Adjust needle size to obtain correct gauge if necessary.

STITCHES AND TECHNIQUES

M1R (make 1 right): With left needle, pick up the strand between 2 stitches from back to front and knit into front loop.

RIBBED NECKBAND

With color B, CO 120 (128, 136, 144, 152) sts. Join, being careful not to twist cast-on row; pm for beginning of rnd.

Half the stitch count by working (k2tog, p2tog) around = 60 (64, 68, 72, 76) sts rem. Now work around in k1, p1 ribbing for approx.

3¼ (4, 4¼, 5¼, 5½) in / 8 (10, 11, 13, 14) cm or desired length.

Knit 1 rnd.

Next, Increase Rnd: (K2, M1R) around = 90 (96, 102, 108, 114) sts.

YOKE

Work around in pattern following chart A.

With color A, knit 1 (1, 1, 2, 2) rnds.

Next, Increase Rnd: (K3, M1R) around = 120 (128, 136, 144, 152) sts.

Knit 1 (1, 2, 2, 3) rnds.

Increase Rnd: (K4, M1R) around = 150 (160, 170, 180, 190) sts.

Knit 1 rnd.

Now work pattern following chart B, working 1 repeat in length.

With color B, continue in garter st: knit 1 rnd, purl 1 rnd, knit 1 rnd, purl 1 rnd, knit 1 rnd. BO purlwise making sure bind off is neither too tight nor too loose.

FINISHING

Weave in all ends neatly on WS.

Block by lightly soaking in lukewarm water; roll in towel to absorb excess water. Lay flat to dry – make sure lower edge doesn't roll up.


SCHEMATICS

A 28 (30, 32, 34, 35½) in / 71 (76, 81, 86, 90) cm

B 8 (8¾, 9½, 10¼, 11) in / 20 (22, 24, 26, 28) cm


C 11½ (11¾, 12¾, 13½, 14¼) in / 29 (30, 32, 34, 36) cm

CHART B



Color A
 Color B
 Color C

CHART A



A ≈ 71 (76) 81 (86) 90 cm
 B ≈ 20 (22) 24 (26) 28 cm
 C ≈ 29 (30) 32 (34) 36 cm



Tips & Shortcuts

To avoid questions: Before you begin knitting, read through the pattern.

Stitch count: Always knit or crochet a gauge swatch as recommended in the pattern. If your stitch count doesn't match the gauge given in the pattern, try again with larger or smaller needles or hook. If your gauge doesn't match that in the pattern, your item will not be the correct size or shape.

Highlight the size you will knit or crochet throughout the pattern to make it easier to follow the instructions.

Charts: It will be easier to follow a chart if you mark your row with a ruler and magnetic board or sticky note.

Ease: The amount of ease included in our garments varies depending on the type and shape of the garment. To determine the right size, we recommend that you first measure your body. Then you can calculate the garment size depending on how much ease you want the garment to have. The schematics for each piece show all the garment measurements.

Two-color stranded knitting: When knitting more than 3-4 stitches of the same color, twist the color strands around each other on the wrong side to avoid long strands or "floats" on the back. If the yarns need to be twisted on several rows/rounds, make sure you do not stack the twists in the same place to prevent the yarns from showing through on the right side.

Yarn alternative: Please be aware that the gauge (tension), yarn quantity and the shape of the work varies if you use another yarn (even in the same yarn group).

Tips for hand dyed yarn: Make sure you have enough yarn to complete your project. The colors may vary from time to time. To get a smooth color mix, you can alternate between two skeins: knit two rows from one and two rows from another skein.

Abbreviations

KNITTING

alt = alternately, **approx.** = approximately, **beg** = begin, **bl** = back loop, **BO** = bind off, **cc** = contrasting color, **cn** = cable needle, **CO** = cast on, **col** = color, **cont** = continue, **dec** = decrease, **dpn(s)** = double-pointed needles, **EOR** = end of row/round, **fl** = front loop, **g st** = garter stitch, **inc** = increase, **k1f&b** = knit in front and back loop of same stitch, **k** = knit (stitch), **k2tog** = knit two stitches together (right-slanting decrease), **kw** = knitwise, **LH** = left hand needle, **m** = marker, **mm** = millimeters, **mc** = main color, **p** = purl (stitch), **patt** = pattern, **pm** = place marker, **pw** = purlwise, **rep** = repeat, **rnd(s)** = round/rounds, **RH** = right hand needle, **RM** = remove marker, **RS** = right side, **sl** = slip, **sl m** = slip marker, **ssk** = slip, slip, knit, **st(s)** = stitches, **St st** = stockinette/stocking stitch, **tog** = together, **WS** = wrong side, **wyib** = with yarn in back, **wyif** = with yarn in front, **yo** = yarn over

CROCHETING

approx. = approximately, **beg** = begin, **bl** = back loop, **ch** = chain stitch, **col** = color, **cont** = continue, **dc** = double crochet, **dec** = decrease, **dtr** = double treble crochet, **fl** = front loop, **hdc** = half double crochet, **htr** = half treble crochet, **inc** = increase, **m** = marker, **mc** = main color, **rep** = repeat, **rnd/rnds** = round/rounds, **RS** = right side, **sc** = single crochet, **sl st** = slip stitch, **sts** = stitches, **tog** = together, **tr** = treble crochet, **tr tr** = triple treble crochet, **WS** = wrong side, **yo** = yarn over