PUMPKIN HOUSE

Crochet pattern

DESIGNED BY ELENA DOROGINA

Facebook: Doroginatoys; Instagram: @dorogina_toys

Thank you for purchasing my pattern!
Enjoy crocheting.
This pattern is a work of authorship, and intends only for personal use!
I appreciate it if you did not share, reproduce or sell this pattern, either in its entirety or in parts!

Note!

Please, note that this pattern does not include the lessons of crocheting. You must have previous knowledge of crochet techniques.

You are welcome to sell the ready product made with this pattern, but credit to **@dorogina_toys** is appreciated. Hashtag **#dorogina_toys** for me to see your ready toy.

CROCHET ABBREVIATIONS (US):

MR – magic ring
CH – chain
SC – single crochet
HDC – half double crochet
DC – double crochet
TR – treble crochet
INC – increase (make 2 sc into one loop)
DEC– decrease (two sc together through front loops)
SL ST – slip stitch
(…)*8 – work instructions within brackets as many times as directed
(18) – the number of *sc* in the row

THE REQUIRED MATERIALS:

DK weight yarn - Alize Cotton Gold (55% cotton/45% acrylic; 100 g/330 m)

- Alize Cotton Gold No. 37, 499 (orange, caramel) – for the pumpkin, stem, and acorns
- Alize Cotton Gold No. 493 (brown) – for the windows, doors, and cupule of the acorns
- Alize Cotton Gold No. 216, 36, 83 (yellow, terracotta, orange) – for the acorns, leaves, and street lantern
- Alize Cotton Gold No. 60 (black) – for the street lantern
- 2.25 mm crochet hook
- Stuffing material (fiberfill/polyester)
- Tapestry needle
- Scissors

- Stitch markers (a scrap of contrasting yarn)
- Pins
- A small piece of wire for the stem of the pumpkin – 6 cm (2.4 inches) long and 1 mm in width.
- A small piece of wire for attaching the bell stem – 3 cm (1.2 inches) long.
- Pliers
- Adhesive tape for the wireframe
- A small piece of yellow and light brown felt for the windows and entrance door
- Glue
- A small metallic bell for the decoration of the door
- A small circle in the diameter of the bottom of the pumpkin (made from cardboard)
- Three small pieces of cardboard for the roof and bottom of the street lantern.

NOTE! Yarn consumption, size, and appearance of the toy depend on crochet density and how you hold the yarn.

The presented toy is crocheted with V and X look single crochet:
(First, you grab yarn over the hook, and for making the second stitch grab it under the hook).

You can crochet with any desired crochet method.

The finished house using the materials stated in this pattern is ~18 cm (7 inches) to the tip of the stem.

Make sure you crochet tight enough, otherwise, the stuffing will show through the holes.

You may use any different yarn brand and color.

ENJOY CROCHETING.

BOTTOM (make 2)

YARN - Alize Cotton Gold No. 37 – (orange)

Rnd 1: 8 into MR
Rnd 2: 8 inc (16)
Rnd 3: (1 sc, inc)*8 (24)
Rnd 4: (2 sc, inc)*8 (32)
Rnd 5: (3 sc, inc)*8 (40)
Rnd 6: (4 sc, inc)*8 (48)
Rnd 7: (5 sc, inc)*8 (56)

Rnd 8: (6 sc, inc)*8 (64), 1 sl st, chain 1

Break yarn.

Crochet the second part similarly. Do not cut yarn on the second part. Trace around the bottom on the cardboard and cut it out.



JOIN THE PARTS

Put two parts together with the right side facing the wrong side and crochet in a round through both loops. Insert the cardboard template as you work.

Rnd 9: (7 sc, inc)*8 (72)

RIGHT SIDE **WRONG SIDE**

NOTE!

In the next rounds of the pumpkin, crochet all increases and decreases through back loops only!

To decrease – skip one stitch and crochet in the second stitch through back loop!

Rnd 10: (8 sc, 1 inc – through back loops)*8 (80)



Rnd 11: (9 sc, 1 inc – through back loops)*8 (88)

Rnd 12: (10 sc, 1 inc - through back loops)*8 (96)

Rnds 13-15: (10 sc through both loops, 2 sc – through back loops)***8** (3 rounds)

** In the next round, crochet increases through back loops only.*

Rnd 16: (11 sc, 1 inc – through back loops)***8** (104)

Rnds 17-24: (11 sc – through both loops, 2 sc – through back loops)***8**
(8 rounds)

Start decreasing from the next round.

To decrease – skip one stitch and crochet 1 sc through back loop in the second stitch.

Rnd 25: (11 sc, 1 dec – through back loops)***4**, (11 sc - through both loops, 2 sc – through back loops)***4** (99)

Rnd 26: (11 sc – through both loops, 1 sc – through back loops)***4**, (11 sc – through both loops, 2 sc – through back loops)***4** (99)

Rnd 27: (10 sc, 1 dec – through back loops)***4**, (11 sc - through both loops,

2 sc – through back loops)***4** (96)

Rnds 28-29: (10 sc – through both loops, 1 sc – through back loops)***4**, (11 sc – through both loops, 2 sc – through back loops)***4** (2 ряда)

Rnd 30: (10 sc – through both loops, 1 sc – through back loops)***4**, (11 sc – through both loops, 1 dec – through back loops)***4** (92)

Rnd 31: (10 sc – through both loops, 1 sc – through back loops)***4**, (11 sc – through both loops, 1 sc – through back loops)***4** (92)

Rnd 32: (10 sc – through both loops, 1 sc – through back loops)***4**, (10 sc – through both loops, 1 dec – through back loops)***4** (88)

Rnd 33: (9 sc – through both loops, 1 dec – through back loops)***8** (80)

Rnd 34: (9 sc – through both loops, 1 sc – through back loops)***8** (80)

Rnd 35: (8 sc – through both loops, 1 dec – through back loops)***8** (72)

Rnds 36-37: (8 sc – through both loops, 1 sc – through back loops)***8** (2 rounds)

Rnd 38: (7 sc – through both loops, 1 dec – through back loops)***8** (64)

Rnds 39-43: (7 sc – through both loops, 1 sc – through back loops)***8** (5 rounds)

Stuff the part with fiberfill.

Note! In the next rounds, decrease and increase to change the tilt of the house.

Increase through back loops only.

*Do not forget to skip one stitch when decreasing and crochet **1 sc** in the second stitch through back loop only.*

Rnd 44: (7 sc – through both loops, 1 inc – through back loops)***4**, (6 sc – through both loops, 1 dec – through back loops)***4** (64)

Rnd 45: (8 sc – through both loops, 1 inc – through back loops)***4**, (5 sc – through both loops, 1 dec – through back loops)***4** (64)

Rnds 46-47: (9 sc – through both loops, 1 sc – through back loops)***4**, (5 sc – through both loops, 1 sc – through back loops)***4** (2 rounds)

Rnd 48: (9 sc – through both loops, 1 inc – through back loops)***4**, (4 sc – through both loops, 1 dec – through back loops)***4** (64)

Rnd 49: (10 sc – through both loops, 1 sc – through back loops)***4**, (4 sc – through both loops, 1 sc – through back loops)***4** (64)

Rnd 50: (9 sc – through both loops, 1 dec – through back loops)***4**, (4 sc – through both loops, 1 sc – through back loops)***4** (60)

Rnd 51: (9 sc – through both loops, 1 sc – through back loops)***4**, (4 sc – through both loops, 1 sc – through back loops)***4** (60)

Rnd 52: (8 sc – through both loops, 1 dec – through back loops)***4**, (4 sc – through both loops, 1 sc – through back loops)***4** (56)

Stuff with fiberfill.

Rnd 53: (7 sc – through both loops, 1 dec – through back loops)***4**, (3 sc – through both loops, 1 dec – through back loops)***4** (48)

Rnd 54: (7 sc – through both loops, 1 sc – through back loops)***4**, (3 sc – through both loops, 1 sc – through back loops)***4** (48)

Rnd 55: (6 sc – through both loops, 1 dec – through back loops)***4**, (2 sc – through both loops, 1 dec – through back loops)***4** (40)

Rnd 56: (5 sc – through both loops, 1 dec – through back loops)***4**, (2 sc – through both loops, 1 sc – through back loops)***4** (36)

Rnd 57: (4 sc – through both loops, 1 dec – through back loops)***4**, (2 sc – through both loops, 1 sc – through back loops)***4** (32)

Rnd 58: (3 sc – through both loops, 1 dec – through back loops)***4**, (2 sc – through both loops, 1 sc – through back loops)***4** (28)

Rnd 59: (2 sc – through both loops, 1 dec – through back loops)***4**, (2 sc – through both loops, 1 sc – through back loops)***4** (24)

Rnd 60: (1 sc – through both loops, 1 dec – through back loops)***8** (16)

**In the last round, decrease through both front loops.*

Rnd 61: (2 sc, dec)***4** (12)

Cut yarn, leaving a long tail for sewing. Stuff with fiberfill. Tighten the hole. Grab 12 front loops with a tapestry needle. Hide the yarn tail inside the pumpkin and cut the excess yarn.

STEM

YARN – Alize cotton Gold No. 499 - (caramel)

Rnd 1: 6 into MR

Rnd 2: 6 inc (12)

** Crochet the next round through back loops only.*

Rnd 3: 12 sc

** Crochet all next rounds through both loops.*

Rnds 4-9: 12 sc (6 rounds)

Rnd 10: (3 sc, inc)*3 (15)

Rnds 11-15: 15 sc (5 rounds)

Rnd 16: (4 sc, inc)*3 (18)

Rnds 17-20: 18 sc (4 rounds)

Rnd 21: (5 sc, inc)*3 (21)

Rnds 22-23: 21 sc (2 rounds)

** Crochet the next round through front loops only.*

Rnd 24: 21 sc, 1 sl st

Cut yarn, leaving a long tail.

Prepare the wireframe for the stem. If the wire is thin and soft – fold it in half a few times.

Wrap around the wireframe with adhesive tape.





Stuff the tip of the stem with fiberfill. Insert the wireframe into the stem and complete stuffing with fiberfill.

Turn the edge around. We will sew the stem to the pumpkin through this round.



Place the stem on the top of the pumpkin, moving it slightly to the right.

Do not place the stem in the center of the closed hole, as it is shifted to the left when crocheting.

Sew the stem to the pumpkin.

Hide the yarn tail inside the pumpkin and cut the excess yarn.

Bend the stem to the right side.

WINDOWS and ENTRANCE DOOR

To make the windows and entrance door, you need the felt in yellow and light brown colors.

YARN - Alize cotton Gold No. 493 (brown).

Draw the template of the windows and entrance door on a piece of paper.



Put the pattern on the felt and trace around it. Cut it out.









WINDOW DESIGN

Embroider the stitches on the windows with a scrap of brown yarn (Alize cotton Gold No. 493. After embroidering, draw the needle to the wrong side and tie the tails together. Cut the excess yarn.











Wrong side.

Crochet the window frame for the upper window with brown yarn.

Chain 35. Try it on the felt template.



Start crocheting in the second chain from hook – **34 HDC.**

Break yarn. Tie the tails together.

Straighten with your fingers, slightly stretch the part, and try it on the window again.

Crochet the window frame for the bottom window with brown yarn.

Chain 30. Try it on the felt template.

Start crocheting in the second chain from hook – **29 HDC.**

Break yarn. Tie the tails together.

Try on the part.

ENTRANCE DOOR

Embroider the doorknob with a scrap of black yarn (Alize cotton Gold No. 60).

Insert the needle from the back of the door. Make two turns of thread onto the needle and insert the needle on the wrong side.

Tie the yarn tails together, and cut the excess yarn.

Prepare a small scrap of brown yarn. The length is about 40 cm (16 inches). Split yarn into two threads.

Embroider the vertical stitches on the prepared felt part.











RIGHT SIDE

WRONG SIDE

Chain 35 with brown yarn (Alize cotton Gold No. 493).
Try it on the felt template of the upper part of the door.

ROOF for the door (make 2)

YARN – Alize cotton Gold No. 493 - (brown)

Chain 8 and start crocheting in the second chain from hook –

1 inc, 5 sc, 4 sc in the last stitch.

Continue crocheting on the other side of the chain foundation – 5 sc, 1 inc (18)

Rnds 2-4: 18 sc (3 rounds)

Cut yarn, leaving a long tail for tightening the hole.
Trace around the part on the cardboard and cut it out. Trim the sharp corners a little.

Insert the template into the part. Join both sides of the part through front loops on the right and left sides.

Fasten off, leaving a long tail for sewing.

ACORN

ACORN No.1

YARN Alize cotton Gold No.499 (caramel)

Rnd 1: 7 into MR

Rnd 2: 7 inc (14)

Rnds 3-7: 14 sc (5 rounds)

Rnd 8: 7 dec (7)

Cut yarn, leaving a long tail.

Stuff with fiberfill. Tighten the hole, grabbing seven front loops with a tapestry needle. Hide the yarn tail inside the acorn.

CUPULE

YARN Alize cotton Gold No.493 (brown)

Rnd 1: 7 into MR

Rnd 2: 7 inc (14)

Rnds 3-6: 14 sc (4 rounds), 1 sl st

Cut yarn, leaving a long tail.

Pull the yarn inside the cap using a tapestry needle and draw the needle to the top of MR. Make a loop.

Chain 5.

Start crocheting in the second chain from hook – **4 sc.**

Pull the needle on the wrong side, fasten off and cut the excess yarn.

Place the cap on the acorn. It is rather hard to put the cap so - screw it around the acorn. Apply a drop of glue under the cap for reliable fixation.

ACORN No.2

YARN Alize cotton Gold No.499 (caramel).

Rnd 1: 7 into MR

Rnd 2: 7 inc (14)

Rmds 3-6: 14 sc (4 rounds)

Rnd 7: 7 dec (7)

Cut yarn, leaving a long tail for sewing.

Stuff with fiberfill. Tighten the hole, grabbing seven front loops using a tapestry needle. Hide the yarn tail inside the acorn.

CAP

YARN Alize cotton Gold No.493 (brown).

Rnd 1: 7 into MR

Rnd 2: 7 inc (14)

Rnds 3-5: 14 sc (3 rounds), 1 sl st

Cut yarn, leaving a long tail.

Pull the yarn inside the cap using a tapestry needle and draw the needle to the top of MR. Make a loop. **Chain 5.**

Start crocheting in the second chain from hook – **4 sc**. Pull the yarn tail to the wrong side, fasten off, and cut the excess yarn.

Put the cap on the acorn and secure it with a drop of glue.

OAK LEAF (make 2)

YARN – Alize cotton Gold No. 36, 83 - (terracotta, orange)

Chain 17. Start crocheting in the second chain from hook –

5 sc, 5 HDC, 5 DC, and 4 DC in the last chain foundation.

Continue crocheting on the other side of the chain foundation – 5 DC, 5 HDC, 5 sc, chain 1 (35)

Rnd 2: 2 sc, 1 HDC, 2 DC, 3 in the chain, 1 sl st in the previous stitch,

2 sc, 1 HDC, 1 DC, 1 TR, chain 4, 1 sl st in the previous stitch,

1 sc, 1 HDC, 1 DC, 1 TR, chain 4, 1 sl st in the previous stitch,

The upper part of the leaf - 1 sc, 1 HDC, (2 DC in a stitch)*2, 1 HDC, 1 sc,

Continue crocheting on the other side of the leaf.

2 sc, chain 4, 1 TR in the previous stitch, 1 DC, 1 HDC, 2 sc,

Chain 4, 1 TR in the previous stitch, 1 DC, 1 HDC, 3 sc,
Chain 3, 1 DC in the previous stitch, 1 HDC, 3 sc,

Crochet the tail of the leaf. **Chain 6.** Start crocheting in the second chain from hook – 5 sc, 1 sl st.

Cut yarn, leaving a long tail for sewing. Pull the yarn tail to the wrong side of the leaf and fasten off, leaving a long tail for sewing.

STREET LANTERN

YARN – Alize cotton Gold No. 216, 60 - (yellow, black)

Crochet the bottom of the lantern with black yarn.

Rnd 1: 8 into MR

Rnd 2: 8 inc (16), 1 sl st

Crochet the next round with Crab «Reverse» stitch.

Crab (Reverse) stitch



Break yarn and pull the tail to the wrong side. Tie the yarn tails together and cut the excess yarn.

RIGHT SIDE **WRONG SIDE**

Crochet the center of the lantern with yellow yarn.

Rnd 1: 8 into MR

Rnd 2: 8 inc (16)

Trace around the part on the cardboard and cut it out.

** Crochet the next round through back loops only.*

Rnd 3: 16 sc



** Crochet the next rounds through both loops.*

Rnds 4-9: 16 sc (6 rounds)

Put the template on the bottom of the part and stuff with fiberfill.

Rnd 10: 8 dec (8)

Cut yarn, leaving a long tail. Do not close the hole.

ASSEMBLY

Prepare a scrap of black yarn 40 cm (16 inches) long. Split yarn into two threads.

Embroider the letter X on four sides. One side is equal to 4 sc. Insert the needle into the hole.



Once you finish embroidering – pull the needle to the top. Tie the yarn tails. Stuff with fiberfill.

Tighten the hole, grabbing eight front loops with a tapestry needle. Hide the yarn tail inside and cut the excess yarn.



Crochet the top of the lantern with black yarn.

Rnd 1: 4 into MR

Rnd 2: 4 sc

Rnd 3: (1 sc, inc)***2** (6)

Rnd 4: (1 sc, inc)*3 (9)

Rnd 5: (2 sc, inc)*3 (12)

Rnd 6: (3 sc, inc)*3 (15)

Rnd 7: (4 sc, inc)*3 (18)

Rnd 8: (5 sc, inc)*3 (21), 1 sl st

Crochet the next round with Crab «Reverse» stitch.

Crab (Reverse) stitch



Cut yarn, leaving a tail 20 cm (8 inches) long. Draw the yarn tail to the wrong side. Fasten off and draw the needle to the top (into the MR).

Join the parts of the lantern.

Glue the parts. Glue the bottom part of the lantern on the wrong side. Do not stuff the upper part.

(Also, you may sew the parts with black sewing thread).

ASSEMBLY

Place the pumpkin facing you. The pumpkin tilts to the right.

To make it convenient to decorate the pumpkin house, put three pins on the back or place a skein of yarn.

1. Put the windows and door on the pumpkin. Glue them.

NOTE! Apply glue on the yarn (embroidered stitches) of the window from the wrong side.

Do not apply glue to the felt - to avoid its saturation on the front side.

2. Put all crocheted parts for the windows and door.

Glue them around the window and upper part of the door.

NOTE! Apply glue on the bottom part and start gluing it carefully, and gradually, a few cm (inches) at a time. Glue it along the edge of the felt.



Hide the yarn tail inside the pumpkin before gluing the bottom part.

Make the second window and door similar.

3. Sew both sides of the roof. Pull the yarn tail diagonally to the lower left corner. Do not cut the thread.

Pin the roof above the door.

Sew it to the pumpkin at three points (in the center and on the sides).





Hide the yarn tails inside the pumpkin.

4. Sew the oak leaves next to the stem of the pumpkin. Apply the leaves on top of each other. After sewing - hide the yarn tail inside the pumpkin.

5. Pin the acorns. Sew them with brown thread or glue them.

6. Make the wireframe for the doorbell.

Cut a piece of wire 3 cm (1.2 inches) long.

Attach the brown yarn (Alize cotton Gold No. 493) or glue it. Wrap it around the wire. Glue the other tail on the wireframe.

Bend one end of the wireframe with pliers. Put the bell.



Attach the doorbell to the pumpkin house.

First, make a small hole at the point of the doorbell with scissors. It will help to insert the wireframe easily.

7. Tie the street lantern to the stem.

Congratulation! Your pumpkin house is finished!
Thank you for purchasing my pattern.